



PX41CX interface



HP41 source program

HILO.txt

001	LBL 'HL' ; Key: 23	C0 00 F3 22 48 4C
002	LBL 05	06
003	XEQ 'ZZ'	1E F2 5A 5A
004	1024	11 10 12 14
005	*	42
006	INT	68
007	STO 01	31
008	1	11
009	STO 05	35
010	FIX 00	9C 00
011	'HI-LO'	F5 48 49 2D 4C 4F
012	PROMPT	8E
013	LBL 01	02
014	RCL 01	21
015	-	41
016	X=0?	67
017	GTO 02	B3 00
018	X>0?	64
019	GTO 03	B4 00
020	X<0?	66
021	GTO 04	B5 00
022	LBL 02	03
023	XEQ 'TO'	1E F2 54 4F
024	FIX 00	9C 00
025	CF 29	A9 1D
026	CLA	87
027	ARCL 05	9B 05
028	>' ESSAIS'	F8 7F 20 45 53 53 41 49 53
029	AVIEW	7E
030	PSE	89
031	SF 29	A8 1D
032	FIX 04	9C 04
033	GTO 05	B6 00
034	LBL 03	04
035	1	11
036	ST+ 05	92 05
037	'PLUS PETIT'	FA 50 4C 55 53 20 50 45 54 49 54
038	PROMPT	8E
039	GTO 01	B2 00
040	LBL 04	05
041	1	11
042	ST+ 05	92 05
043	'PLUS GRAND'	FA 50 4C 55 53 20 47 52 41 4E 44
044	PROMPT	8E
045	GTO 01	B2 00
046	LBL 'ZZ'	C0 00 F3 00 5A 5A
047	RCL 00	20
048	FRC	69
049	X=0?	67
050	TIME	A6 9C
051	PI	72
052	+	40
053	5	15

054	Y^X	53
055	FRC	69
056	STO 00	30
057	RTN	85
058	LBL 'TO'	C0 00 F3 00 54 4F
059	TONE 08	9F 08
060	TONE 08	9F 08
061	TONE 08	9F 08
062	TONE 07	9F 07
063	TONE 08	9F 08
064	TONE 08	9F 08
065	TONE 07	9F 07
066	TONE 08	9F 08
067	TONE 09	9F 09
068	TONE 09	9F 09
069	TONE 08	9F 08
070	TONE 08	9F 08
071	TONE 07	9F 07
072	TONE 07	9F 07
073	TONE 06	9F 06
074	RTN	85
075	END	C0 00 0D



PX41CX interface



Program : HILO

Row 1 (Lines 1-4)



Row 2 (Lines 4-11)



Row 3 (Lines 11-20)




Row 4 (Lines 21-27)



Row 5 (Lines 27-31)



Row 6 (Lines 31-37)




Row 7 (Lines 37-42)



Row 8 (Lines 42-44)



Row 9 (Lines 45-50)



Row 10 (Lines 51-58)



Row 11 (Lines 58-65)



Row 12 (Lines 65-71)



Row 13 (Lines 72-75)



End of Bar Code - Total of 13 Rows