



PX41CX interface



HP41 source program

PI.txt

001	LBL 'PI1' ; Key: 11	C0 00 F4 01 50 49 31
002	FIX 9	9C 09
003	7	17
004	ENTER	83
005	6	16
006	ENTER	83
007	5	15
008	SQRT	52
009	+	40
010	SQRT	52
011	+	40
012	SQRT	52
013	STOP	84
014	LBL 'PI2' ; Key: 12	C0 00 F4 11 50 49 32
015	FIX 9	9C 09
016	1	11
017	.	1A
018	8	18
019	SQRT	52
020	LASTX	76
021	+	40
022	STOP	84
023	LBL 'PI3' ; Key: 13	C0 00 F4 21 50 49 33
024	FIX 9	9C 09
025	3	13
026	5	15
027	5	15
028	ENTER	83
029	1	11
030	1	11
031	3	13
032	/	43
033	STOP	84
034	LBL 'PI4' ; Key: 14	C0 00 F4 31 50 49 34
035	FIX 9	9C 09
036	2	12
037	1	11
038	.	1A
039	9	19
040	9	19
041	1	11
042	ENTER	83
043	7	17
044	/	43
045	STOP	84
046	LBL 'PI5' ; Key: 15	C0 00 F4 41 50 49 35
047	FIX 9	9C 09
048	9801	19 18 10 11
049	ENTER	83
050	1103	11 11 10 13
051	ENTER	83
052	8	18
053	SQRT	52

054	*	42
055	/	43
056	STOP	84
057	LBL 'PI6' ; Key: 21	C0 00 F4 02 50 49 36
058	FIX 9	9C 09
059	8	18
060	SQRT	52
061	SQRT	52
062	SQRT	52
063	SQRT	52
064	SQRT	52
065	SQRT	52
066	SQRT	52
067	SQRT	52
068	SQRT	52
069	SQRT	52
070	SQRT	52
071	SQRT	52
072	SQRT	52
073	SQRT	52
074	SQRT	52
075	SQRT	52
076	SQRT	52
077	SQRT	52
078	SQRT	52
079	SQRT	52
080	SQRT	52
081	SQRT	52
082	SQRT	52
083	SQRT	52
084	SQRT	52
085	SQRT	52
086	SQRT	52
087	SQRT	52
088	1	11
089	4	14
090	SQRT	52
091	SQRT	52
092	SQRT	52
093	SQRT	52
094	SQRT	52
095	SQRT	52
096	SQRT	52
097	SQRT	52
098	SQRT	52
099	SQRT	52
100	SQRT	52
101	SQRT	52
102	6	16
103	8	18
104	SQRT	52
105	SQRT	52
106	SQRT	52
107	SQRT	52
108	SQRT	52
109	+	40
110	+	40
111	STOP	84
112	LBL 'PIGAP' ; Key: 25	C0 00 F6 42 50 49 47 41 50
113	FIX 9	9C 09
114	PI	72
115	-	41
116	STOP	84



PX41CX interface



Program : PI

Row 1 (Lines 1-6)



Row 2 (Lines 7-14)



Row 3 (Lines 14-21)



Row 4 (Lines 21-25)



Row 5 (Lines 25-30)



Row 6 (Lines 30-35)



Row 7 (Lines 35-39)



Row 8 (Lines 39-46)



Row 9 (Lines 46-58)



Row 10 (Lines 59-71)



Row 11 (Lines 72-83)



Row 12 (Lines 84-95)



Row 13 (Lines 96-100)



Row 14 (Lines 100-104)



End of Bar Code - Total of 14 Rows